

util-vserver (libvserver) Reference Manual
0.30.216-pre2883

Generated by Doxygen 1.4.4

Fri May 7 06:24:46 2010

Contents

1	util-vserver (libvserver) Module Index	1
2	util-vserver (libvserver) Data Structure Index	1
3	util-vserver (libvserver) File Index	2
4	util-vserver (libvserver) Module Documentation	2
5	util-vserver (libvserver) Data Structure Documentation	10
6	util-vserver (libvserver) File Documentation	18

1 util-vserver (libvserver) Module Index

1.1 util-vserver (libvserver) Modules

Here is a list of all modules:

Syscall wrappers	2
Helper functions	8

2 util-vserver (libvserver) Data Structure Index

2.1 util-vserver (libvserver) Data Structures

Here are the data structures with brief descriptions:

Mapping_uint32	10
Mapping_uint64	10
vc_ctx_caps (Capabilities of process-contexts)	11
vc_ctx_dlimit	11
vc_ctx_flags (Flags of process-contexts)	12
vc_ctx_stat (Statistics about a context)	12
vc_err_listparser (Information about parsing errors)	13
vc_ip_mask_pair	13
vc_net_addr	14
vc_net_caps	14

vc_net_flags	14
vc_nx_info	15
vc_rlimit (The limits of a resources)	15
vc_rlimit_mask (Masks describing the supported limits)	16
vc_rlimit_stat (Statistics for a resource limit)	16
vc_sched_info	17
vc_set_sched	17
vc_virt_stat (Contains further statistics about a context)	18
vc_vx_info	18

3 util-vserver (libvserver) File Index

3.1 util-vserver (libvserver) File List

Here is a list of all documented files with brief descriptions:

internal.h (Declarations which are used by util-vserver internally)	18
vserver.h (The public interface of the the libvserver library)	20

4 util-vserver (libvserver) Module Documentation

4.1 Syscall wrappers

Functions

- [int vc_syscall](#) (uint32_t cmd, [xid_t](#) xid, void *data)
The generic vserver syscall
This function executes the generic vserver syscall. It uses the correct syscallnumber (which may differ between the different architectures).
- [int vc_get_version](#) ()
Returns the version of the current kernel API.
- [vc_vci_t vc_get_vci](#) ()
Returns the kernel configuration bits.
- [xid_t vc_new_s_context](#) ([xid_t](#) ctx, unsigned int remove_cap, unsigned int flags)
Moves current process into a context
Puts current process into context ctx, removes the capabilities given in remove_cap and sets flags.
- [int vc_set_ipv4root](#) (uint32_t bcast, size_t nb, struct [vc_ip_mask_pair](#) const *ips)
Sets the ipv4root information.

- `xid_t vc_ctx_create (xid_t xid, struct vc_ctx_flags *flags)`
*Creates a context without starting it.
This functions initializes a new context. When already in a freshly created context, this old context will be discarded.*
- `int vc_ctx_migrate (xid_t xid, uint_least64_t flags)`
Moves the current process into the specified context.
- `int vc_ctx_stat (xid_t xid, struct vc_ctx_stat *stat)`
Get some statistics about a context.
- `int vc_virt_stat (xid_t xid, struct vc_virt_stat *stat)`
Get more statistics about a context.
- `int vc_ctx_kill (xid_t ctx, pid_t pid, int sig)`
*Sends a signal to a context/pid
Special values for pid are:*
 - -1 which means every process in ctx except the init-process
 - 0 which means every process in ctx inclusive the init-process.
- `xid_t vc_get_task_xid (pid_t pid)`
Returns the context of the given process.
- `int vc_wait_exit (xid_t xid)`
Waits for the end of a context.
- `int vc_get_rlimit (xid_t xid, int resource, struct vc_rlimit *lim)`
Returns the limits of resource.
- `int vc_set_rlimit (xid_t xid, int resource, struct vc_rlimit const *lim)`
Sets the limits of resource.
- `int vc_rlimit_stat (xid_t xid, int resource, struct vc_rlimit_stat *stat)`
Returns the current stats of resource.
- `int vc_reset_minmax (xid_t xid)`
Resets the minimum and maximum observed values of all resources.
- `int vc_get_iattr (char const *filename, xid_t *xid, uint_least32_t *flags, uint_least32_t *mask)`
*Returns information about attributes and assigned context of a file.
This function returns the VC_IATTR_XXX flags and about the assigned context of a file. To request an information, the appropriate bit in mask must be set and the corresponding parameter (xid or flags) must not be NULL.*
- `xid_t vc_getfilecontext (char const *filename)`
*Returns the context of filename
This function calls `vc_get_iattr()` with appropriate arguments to determine the context of filename. In error-case or when no context is assigned, VC_NOCTX will be returned. To differ between both cases, `errno` must be examined.*

4.1.1 Detailed Description

Functions which are calling the vserver syscall directly.

4.1.2 Function Documentation

4.1.2.1 `xid_t vc_ctx_create (xid_t xid, struct vc_ctx_flags * flags)`

Creates a context without starting it.

This functions initializes a new context. When already in a freshly created context, this old context will be discarded.

Parameters:

xid The new context; special values are:

- VC_DYNAMIC_XID which means to create a dynamic context

Returns:

the xid of the created context, or VC_NOCTX on errors. `errno` will be set appropriately.

4.1.2.2 `int vc_ctx_migrate (xid_t xid, uint_least64_t flags)`

Moves the current process into the specified context.

Parameters:

xid The new context

flags The flags, see VC_VXM_*

Returns:

0 on success, -1 on errors

4.1.2.3 `int vc_ctx_stat (xid_t xid, struct vc_ctx_stat * stat)`

Get some statistics about a context.

Parameters:

xid The context to get stats about

stat Where to store the result

Returns:

0 on success, -1 on errors.

4.1.2.4 `int vc_get_iattr (char const * filename, xid_t * xid, uint_least32_t * flags, uint_least32_t * mask)`

Returns information about attributes and assigned context of a file.

This function returns the VC_IATTR_XXX flags and about the assigned context of a file. To request an information, the appropriate bit in `mask` must be set and the corresponding parameter (*xid* or *flags*) must not be NULL.

E.g. to receive the assigned context, the VC_IATTR_XID bit must be set in *mask*, and *xid* must point to valid memory.

Possible flags are VC_IATTR_ADMIN, VC_IATTR_WATCH , VC_IATTR_HIDE, VC_IATTR_BARRIER, VC_IATTR_IUNLINK and VC_IATTR_IMMUTABLE.

Parameters:

filename The name of the file whose attributes shall be determined.

xid When non-zero and the VC_IATTR_XID bit is set in *mask*, the assigned context of *filename* will be stored there.

flags When non-zero, a bitmask of current attributes will be stored there. These attributes must be requested explicitly by setting the appropriate bit in *mask*

mask Points to a bitmask which tells which attributes shall be determined. On return, it will masquerade the attributes which were determined.

Precondition:

`mask!=0 && !((*mask&VC_IATTR_XID) && xid==0) && !((*mask&~VC_IATTR_XID) && flags==0)`

4.1.2.5 int vc_get_rlimit (xid_t xid, int resource, struct vc_rlimit * lim)

Returns the limits of *resource*.

Parameters:

xid The id of the context

resource The resource which will be queried

lim The result which will be filled with the limits

Returns:

0 on success, and -1 on errors.

4.1.2.6 xid_t vc_get_task_xid (pid_t pid)

Returns the context of the given process.

Parameters:

pid the process-id whose xid shall be determined; pid==0 means the current process.

Returns:

the xid of process *pid* or -1 on errors

4.1.2.7 vc_vci_t vc_get_vci ()

Returns the kernel configuration bits.

Returns:

The kernel configuration bits

4.1.2.8 int vc_get_version ()

Returns the version of the current kernel API.

Returns:

The versionnumber of the kernel API

4.1.2.9 **xid_t** vc_getfilecontext (char const **filename*)

Returns the context of *filename*

This function calls [vc_get_iattr\(\)](#) with appropriate arguments to determine the context of *filename*. In error-case or when no context is assigned, VC_NOCTX will be returned. To differ between both cases, *errno* must be examined.

WARNING: this function can modify *errno* although no error happened.

Parameters:

filename The file to check

Returns:

The assigned context, or VC_NOCTX when an error occurred or no such assignment exists. *errno* will be 0 in the latter case

4.1.2.10 **xid_t** vc_new_s_context (**xid_t** *ctx*, unsigned int *remove_cap*, unsigned int *flags*)

Moves current process into a context

Puts current process into context *ctx*, removes the capabilities given in *remove_cap* and sets *flags*.

Parameters:

ctx The new context; special values for are

- VC_SAMECTX which means the current context (just for changing caps and flags)
- VC_DYNAMIC_XID which means the next free context; this value can be used by ordinary users also

remove_cap The linux capabilities which will be **removed**.

flags Special flags which will be set.

Returns:

The new context-id, or VC_NOCTX on errors; *errno* will be set appropriately

See <http://vserver.13thfloor.at/Stuff/Logic.txt> for details

4.1.2.11 int vc_reset_minmax (**xid_t** *xid*)

Resets the minimum and maximum observed values of all resources.

Parameters:

xid The id of the context

Returns:

0 on success, and -1 on errors.

4.1.2.12 `int vc_rlimit_stat (xid_t xid, int resource, struct vc_rlimit_stat * stat)`

Returns the current stats of *resource*.

Parameters:

- xid* The id of the context
- resource* The resource which will be queried
- stat* The result which will be filled with the stats

Returns:

0 on success, and -1 on errors.

4.1.2.13 `int vc_set_ipv4root (uint32_t bcast, size_t nb, struct vc_ip_mask_pair const * ips)`

Sets the ipv4root information.

Precondition:

nb < NB_IPV4ROOT && *ips* != 0

4.1.2.14 `int vc_set_rlimit (xid_t xid, int resource, struct vc_rlimit const * lim)`

Sets the limits of *resource*.

Parameters:

- xid* The id of the context
- resource* The resource which will be queried
- lim* The new limits

Returns:

0 on success, and -1 on errors.

4.1.2.15 `int vc_syscall (uint32_t cmd, xid_t xid, void * data)`

The generic vserver syscall

This function executes the generic vserver syscall. It uses the correct syscallnumber (which may differ between the different architectures).

Parameters:

- cmd* the command to be executed
- xid* the xid on which the cmd shall be applied
- data* additional arguments; depends on *cmd*

Returns:

depends on *cmd*; usually, -1 stands for an error

4.1.2.16 `int vc_virt_stat (xid_t xid, struct vc_virt_stat * stat)`

Get more statistics about a context.

Parameters:

- xid* The context to get stats about
- stat* Where to store the result

Returns:

0 on success, -1 on errors.

4.2 Helper functions**Data Structures**

- struct `vc_err_listparser`
Information about parsing errors.

Functions

- `size_t vc_get_nb_ipv4root ()` `VC_ATTR_CONST`
*Returns the value of NB_IPV4ROOT.
This function returns the value of NB_IPV4ROOT which was used when the library was built, but **not** the value which is used by the currently running kernel.*
- `bool vc_parseLimit (char const *str, vc_limit_t *res)`
*Parses a string describing a limit
This function parses str and interprets special words like "inf" or suffixes. Valid suffixes are*
 - k ... 1000
 - m ... 1000000
 - K ... 1024
 - M ... 1048576.
- `uint_least64_t vc_text2bcap (char const *str, size_t len)`
Converts a single string into bcapability.
- `char const * vc_lobcap2text (uint_least64_t *val)`
Converts the lowest bit of a bcapability or the entire value (when possible) to a textual representation.
- `int vc_list2bcap (char const *str, size_t len, struct vc_err_listparser *err, struct vc_ctx_caps *cap)`
*Converts a string into a bcapability-bitmask
Syntax of str:.*

4.2.1 Detailed Description

Functions which are doing general helper tasks like parameter parsing.

4.2.2 Function Documentation

4.2.2.1 `int vc_list2bcap (char const * str, size_t len, struct vc_err_listparser * err, struct vc_ctx_caps * cap)`

Converts a string into a bcapability-bitmask

Syntax of *str*:

```
LIST    <- ELEM | ELEM ' , ' LIST
ELEM    <- '~' ELEM | MASK | NAME
MASK    <- NUMBER | '^' NUMBER
NUMBER  <- 0[0-7]* | [1-9][0-9]* | 0x[0-9,a-f]+
NAME    <- <literal name> | "all" | "any" | "none"
```

When the '~' prefix is used, the bits will be unset and a '~' after another '~' will cancel both ones. The '^' prefix specifies a bitnumber instead of a bitmask.

"literal name" is everything which will be accepted by the `vc_text2bcap()` function. The special values for NAME will be recognized case insensitively

Parameters:

str The string to be parsed

len The length of the string, or 0 for automatic detection

err Pointer to a structure for error-information, or NULL.

cap Pointer to a `vc_ctx_caps` structure holding the results; only the *bcaps* and *bmask* fields will be changed and already set values will not be honored. When an error occurred, *cap* will have the value of all processed valid BCAP parts.

Returns:

0 on success, -1 on error. In error case, *err* will hold position and length of the first not understood BCAP part

Precondition:

str != 0 && *cap* != 0; *cap*->*bcaps* and *cap*->*bmask* must be initialized

4.2.2.2 `char const* vc_lobcap2text (uint_least64_t * val)`

Converts the lowest bit of a bcapability or the entire value (when possible) to a textual representation.

Parameters:

val The string to be converted; on success, the detected bit(s) will be unset, in errorcase only the lowest set bit

Returns:

A textual representation of *val* resp. of its lowest set bit; or NULL in errorcase.

Precondition:

val != 0

Postcondition:

```
*valold != 0 <-> *valold > *valnew
*valold == 0 --> result == 0
```

4.2.2.3 bool vc_parseLimit (char const * *str*, [vc_limit_t](#) * *res*)

Parses a string describing a limit

This function parses *str* and interprets special words like "inf" or suffixes. Valid suffixes are

- k ... 1000
- m ... 1000000
- K ... 1024
- M ... 1048576.

Parameters:

str The string which shall be parsed

res Will be filled with the interpreted value; in errorcase, this value is undefined.

Returns:

true, iff the string *str* could be parsed. *res* will be filled with the interpreted value in this case.

Precondition:

str!=0 && *res*!=0

4.2.2.4 uint_least64_t vc_text2bcap (char const * *str*, size_t *len*)

Converts a single string into bcability.

Parameters:

str The string to be parsed; both "CAP_XXX" and "XXX" will be accepted

len The length of the string, or 0 for automatic detection

Returns:

0 on error; a bitmask on success

Precondition:

str != 0

5 util-vserver (libvserver) Data Structure Documentation

5.1 Mapping_uint32 Struct Reference

Data Fields

- char const *const [id](#)
- size_t [len](#)
- uint_least32_t [val](#)

5.1.1 Detailed Description

Definition at line 80 of file internal.h.

The documentation for this struct was generated from the following file:

- [internal.h](#)

5.2 Mapping_uint64 Struct Reference

Data Fields

- char const *const [id](#)
- size_t [len](#)
- uint_least64_t [val](#)

5.2.1 Detailed Description

Definition at line 86 of file internal.h.

The documentation for this struct was generated from the following file:

- [internal.h](#)

5.3 vc_ctx_caps Struct Reference

Capabilities of process-contexts.

```
#include <vserver.h>
```

Data Fields

- uint_least64_t [bcaps](#)
Mask of set common system capabilities.
- uint_least64_t [bmask](#)
Mask of set and unset common system capabilities when used by set operations, or the modifiable capabilities when used by get operations.
- uint_least64_t [ccaps](#)
Mask of set process context capabilities.
- uint_least64_t [cmask](#)
Mask of set and unset process context capabilities when used by set operations, or the modifiable capabilities when used by get operations.

5.3.1 Detailed Description

Capabilities of process-contexts.

Definition at line 504 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.4 vc_ctx_dlimit Struct Reference

Data Fields

- uint_least32_t [space_used](#)
- uint_least32_t [space_total](#)
- uint_least32_t [inodes_used](#)
- uint_least32_t [inodes_total](#)
- uint_least32_t [reserved](#)

5.4.1 Detailed Description

Definition at line 781 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.5 vc_ctx_flags Struct Reference

Flags of process-contexts.

```
#include <vserver.h>
```

Data Fields

- uint_least64_t [flagword](#)
Mask of set context flags.
- uint_least64_t [mask](#)
Mask of set and unset context flags when used by set operations, or modifiable flags when used by get operations.

5.5.1 Detailed Description

Flags of process-contexts.

Definition at line 426 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.6 vc_ctx_stat Struct Reference

Statistics about a context.

```
#include <vserver.h>
```

Data Fields

- `uint_least32_t usecnt`
number of uses
- `uint_least32_t tasks`
number of tasks

5.6.1 Detailed Description

Statistics about a context.

Definition at line 457 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.7 `vc_err_listparser` Struct Reference

Information about parsing errors.

```
#include <vserver.h>
```

Data Fields

- `char const * ptr`
Pointer to the first character of an erroneous string.
- `size_t len`
Length of the erroneous string.

5.7.1 Detailed Description

Information about parsing errors.

Definition at line 856 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.8 `vc_ip_mask_pair` Struct Reference

Data Fields

- `uint32_t ip`
- `uint32_t mask`

5.8.1 Detailed Description

Definition at line 404 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.9 vc_net_addr Struct Reference

Data Fields

- uint16_t [vna_type](#)
- uint16_t [vna_flags](#)
- uint16_t [vna_prefix](#)
- uint16_t [vna_parent](#)
- struct {
 - union {
 - [in_addr v4](#)
 - [in6_addr v6](#)
 - ip**
 - union {
 - [in_addr v4](#)
 - [in6_addr v6](#)
 - ip2**
 - union {
 - [in_addr v4](#)
 - [in6_addr v6](#)
 - mask**
- s**

5.9.1 Detailed Description

Definition at line 654 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.10 vc_net_caps Struct Reference

Data Fields

- uint_least64_t [ncaps](#)
- uint_least64_t [cmask](#)

5.10.1 Detailed Description

Definition at line 695 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.11 `vc_net_flags` Struct Reference

Data Fields

- `uint_least64_t` [flagword](#)
- `uint_least64_t` [mask](#)

5.11.1 Detailed Description

Definition at line 681 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.12 `vc_nx_info` Struct Reference

Data Fields

- `nid_t` [nid](#)

5.12.1 Detailed Description

Definition at line 647 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.13 `vc_rlimit` Struct Reference

The limits of a resources.

```
#include <vserver.h>
```

Data Fields

- `vc_limit_t` [min](#)
the guaranted minimum of a resources
- `vc_limit_t` [soft](#)
the softlimit of a resource
- `vc_limit_t` [hard](#)
the absolute hardlimit of a resource

5.13.1 Detailed Description

The limits of a resources.

This is a triple consisting of a minimum, soft and hardlimit.

Definition at line 570 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.14 `vc_rlimit_mask` Struct Reference

Masks describing the supported limits.

```
#include <vserver.h>
```

Data Fields

- `uint_least32_t min`
masks the resources supporting a minimum limit
- `uint_least32_t soft`
masks the resources supporting a soft limit
- `uint_least32_t hard`
masks the resources supporting a hard limit

5.14.1 Detailed Description

Masks describing the supported limits.

Definition at line 557 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.15 `vc_rlimit_stat` Struct Reference

Statistics for a resource limit.

```
#include <vserver.h>
```

Data Fields

- `uint_least32_t hits`
number of hits on the limit
- `vc_limit_t value`

current value

- [vc_limit_t minimum](#)

minimum value observed

- [vc_limit_t maximum](#)

maximum value observed

5.15.1 Detailed Description

Statistics for a resource limit.

Definition at line 598 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.16 vc_sched_info Struct Reference

Data Fields

- [int_least32_t cpu_id](#)
- [int_least32_t bucket_id](#)
- [uint_least64_t user_msec](#)
- [uint_least64_t sys_msec](#)
- [uint_least64_t hold_msec](#)
- [uint_least32_t token_usec](#)
- [int_least32_t vavavoom](#)

5.16.1 Detailed Description

Definition at line 833 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.17 vc_set_sched Struct Reference

Data Fields

- [uint_least32_t set_mask](#)
- [int_least32_t fill_rate](#)
- [int_least32_t interval](#)
- [int_least32_t fill_rate2](#)
- [int_least32_t interval2](#)
- [int_least32_t tokens](#)
- [int_least32_t tokens_min](#)
- [int_least32_t tokens_max](#)

- [int_least32_t priority_bias](#)
- [int_least32_t cpu_id](#)
- [int_least32_t bucket_id](#)

5.17.1 Detailed Description

Definition at line 816 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.18 vc_virt_stat Struct Reference

Contains further statistics about a context.

```
#include <vserver.h>
```

Data Fields

- [uint_least64_t offset](#)
- [uint_least64_t uptime](#)
- [uint_least32_t nr_threads](#)
- [uint_least32_t nr_running](#)
- [uint_least32_t nr_uninterruptible](#)
- [uint_least32_t nr_onhold](#)
- [uint_least32_t nr_forks](#)
- [uint_least32_t load](#) [3]

5.18.1 Detailed Description

Contains further statistics about a context.

Definition at line 472 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.19 vc_vx_info Struct Reference

Data Fields

- [xid_t xid](#)
- [pid_t initpid](#)

5.19.1 Detailed Description

Definition at line 522 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)


6 util-vserver (libvserver) File Documentation

6.1 internal.h File Reference

Declarations which are used by util-vserver internally.

```
#include "fmt.h"
#include "vserver.h"
#include <stdlib.h>
#include <stdbool.h>
```

Include dependency graph for internal.h:



Data Structures

- struct [Mapping_uint32](#)
- struct [Mapping_uint64](#)

Defines

- #define [_symbol_version](#)(real, name, version)
- #define [_default_symbol_version](#)(real, name, version) extern __typeof (real) name __attribute__((alias (#name)));
- #define [symbol_version](#)(real, name, version) _symbol_version(real, name, version)
- #define [default_symbol_version](#)(real, name, version) _default_symbol_version(real, name, version)

Functions

- char * [vc_getVserverByCtx_Internal](#) (xid_t ctx, [vcCfgStyle](#) *style, char const *revdir, bool validate_result)
- int [utilvserver_checkCompatVersion](#) ()
- uint_least32_t [utilvserver_checkCompatConfig](#) ()
- bool [utilvserver_isDirectory](#) (char const *path, bool follow_link)
- bool [utilvserver_isFile](#) (char const *path, bool follow_link)
- bool [utilvserver_isLink](#) (char const *path)
- int [utilvserver_listparser_uint32](#) (char const *str, size_t len, char const **err_ptr, size_t *err_len, uint_least32_t *flag, uint_least32_t *mask, uint_least32_t(*func)(char const *, size_t, bool *)) NONNULL((1

- int int **utilvserver_listparser_uint64** (char const *str, size_t len, char const **err_ptr, size_t *err_len, uint_least64_t *flag, uint_least64_t *mask, uint_least64_t(*func)(char const *, size_t, bool *)) NONNULL((1
- ssize_t **utilvserver_value2text_uint32** (char const *str, size_t len, struct [Mapping_uint32](#) const *map, size_t map_len) NONNULL((1
- ssize_t ssize_t **utilvserver_value2text_uint64** (char const *str, size_t len, struct [Mapping_uint64](#) const *map, size_t map_len) NONNULL((1
- ssize_t ssize_t ssize_t **utilvserver_text2value_uint32** (uint_least32_t *val, struct [Mapping_uint32](#) const *map, size_t map_len) NONNULL((1
- ssize_t ssize_t ssize_t ssize_t **utilvserver_text2value_uint64** (uint_least64_t *val, struct [Mapping_uint64](#) const *map, size_t map_len) NONNULL((1

6.1.1 Detailed Description

Declarations which are used by util-vserver internally.


Definition in file [internal.h](#).

6.2 vserver.h File Reference

The public interface of the the libvserver library.

```
#include <stdint.h>
#include <stdlib.h>
#include <stdbool.h>
#include <sys/types.h>
#include <sched.h>
#include <netinet/in.h>
```

Include dependency graph for vserver.h:



This graph shows which files directly or indirectly include this file:



Data Structures

- struct [vc_ip_mask_pair](#)
- struct [vc_ctx_flags](#)
Flags of process-contexts.
- struct [vc_ctx_stat](#)
Statistics about a context.
- struct [vc_virt_stat](#)
Contains further statistics about a context.
- struct [vc_ctx_caps](#)
Capabilities of process-contexts.
- struct [vc_vx_info](#)
- struct [vc_rlimit_mask](#)
Masks describing the supported limits.
- struct [vc_rlimit](#)
The limits of a resources.
- struct [vc_rlimit_stat](#)
Statistics for a resource limit.
- struct [vc_nx_info](#)
- struct [vc_net_addr](#)
- struct [vc_net_flags](#)
- struct [vc_net_caps](#)
- struct [vc_ctx_dlimit](#)
- struct [vc_set_sched](#)
- struct [vc_sched_info](#)
- struct [vc_err_listparser](#)
Information about parsing errors.

Defines

- #define [VC_NOCTX](#) ((xid_t)(-1))
- #define [VC_NOXID](#) ((xid_t)(-1))
- #define [VC_DYNAMIC_XID](#) ((xid_t)(-1))
- #define [VC_SAMECTX](#) ((xid_t)(-2))
- #define [VC_NONID](#) ((nid_t)(-1))
- #define [VC_DYNAMIC_NID](#) ((nid_t)(-1))
- #define [VC_LIM_INFINITY](#) (~0ULL)
- #define [VC_LIM_KEEP](#) (~1ULL)
- #define [VC_CDLIM_UNSET](#) (0U)
- #define [VC_CDLIM_INFINITY](#) (~0U)
- #define [VC_CDLIM_KEEP](#) (~1U)
- #define [S_CTX_INFO_LOCK](#) 1

- #define [S_CTX_INFO_SCHED](#) 2
- #define [S_CTX_INFO_NPROC](#) 4
- #define [S_CTX_INFO_PRIVATE](#) 8
- #define [S_CTX_INFO_INIT](#) 16
- #define [S_CTX_INFO_HIDEINFO](#) 32
- #define [S_CTX_INFO_ULIMIT](#) 64
- #define [S_CTX_INFO_NAMESPACE](#) 128
- #define [VC_CAP_CHOWN](#) 0
- #define [VC_CAP_DAC_OVERRIDE](#) 1
- #define [VC_CAP_DAC_READ_SEARCH](#) 2
- #define [VC_CAP_FOWNER](#) 3
- #define [VC_CAP_FSETID](#) 4
- #define [VC_CAP_KILL](#) 5
- #define [VC_CAP_SETGID](#) 6
- #define [VC_CAP_SETUID](#) 7
- #define [VC_CAP_SETPCAP](#) 8
- #define [VC_CAP_LINUX_IMMUTABLE](#) 9
- #define [VC_CAP_NET_BIND_SERVICE](#) 10
- #define [VC_CAP_NET_BROADCAST](#) 11
- #define [VC_CAP_NET_ADMIN](#) 12
- #define [VC_CAP_NET_RAW](#) 13
- #define [VC_CAP_IPC_LOCK](#) 14
- #define [VC_CAP_IPC_OWNER](#) 15
- #define [VC_CAP_SYS_MODULE](#) 16
- #define [VC_CAP_SYS_RAWIO](#) 17
- #define [VC_CAP_SYS_CHROOT](#) 18
- #define [VC_CAP_SYS_PTRACE](#) 19
- #define [VC_CAP_SYS_PACCT](#) 20
- #define [VC_CAP_SYS_ADMIN](#) 21
- #define [VC_CAP_SYS_BOOT](#) 22
- #define [VC_CAP_SYS_NICE](#) 23
- #define [VC_CAP_SYS_RESOURCE](#) 24
- #define [VC_CAP_SYS_TIME](#) 25
- #define [VC_CAP_SYS_TTY_CONFIG](#) 26
- #define [VC_CAP_MKNOD](#) 27
- #define [VC_CAP_LEASE](#) 28
- #define [VC_CAP_AUDIT_WRITE](#) 29
- #define [VC_CAP_AUDIT_CONTROL](#) 30
- #define [VC_CAP_SETFCAP](#) 31
- #define [VC_CAP_MAC_OVERRIDE](#) 32
- #define [VC_CAP_MAC_ADMIN](#) 33
- #define [VC_IMMUTABLE_FILE_FL](#) 0x0000010lu
- #define [VC_IMMUTABLE_LINK_FL](#) 0x0008000lu
- #define [VC_IMMUTABLE_ALL](#) (VC_IMMUTABLE_LINK_FL|VC_IMMUTABLE_FILE_FL)
- #define [VC_IATTR_XID](#) 0x01000000u
- #define [VC_IATTR_ADMIN](#) 0x00000001u
- #define [VC_IATTR_WATCH](#) 0x00000002u
- #define [VC_IATTR_HIDE](#) 0x00000004u
- #define [VC_IATTR_WRITE](#) 0x00000008u
- #define [VC_IATTR_FLAGS](#) 0x0000000fu

- #define VC_IATTR_BARRIER 0x00010000u
- #define VC_IATTR_IUNLINK 0x00020000u
- #define VC_IATTR_IMMUTABLE 0x00040000u
- #define VC_IATTR_COW 0x00080000u
- #define VC_VXF_INFO_LOCK 0x00000001ull
- #define VC_VXF_INFO_NPROC 0x00000004ull
- #define VC_VXF_INFO_PRIVATE 0x00000008ull
- #define VC_VXF_INFO_INIT 0x00000010ull
- #define VC_VXF_INFO_HIDEINFO 0x00000020ull
- #define VC_VXF_INFO_ULIMIT 0x00000040ull
- #define VC_VXF_INFO_NAMESPACE 0x00000080ull
- #define VC_VXF_SCHED_HARD 0x00000100ull
- #define VC_VXF_SCHED_PRIO 0x00000200ull
- #define VC_VXF_SCHED_PAUSE 0x00000400ull
- #define VC_VXF_VIRT_MEM 0x00010000ull
- #define VC_VXF_VIRT_UPTIME 0x00020000ull
- #define VC_VXF_VIRT_CPU 0x00040000ull
- #define VC_VXF_VIRT_LOAD 0x00080000ull
- #define VC_VXF_VIRT_TIME 0x00100000ull
- #define VC_VXF_HIDE_MOUNT 0x01000000ull
- #define VC_VXF_HIDE_NETIF 0x02000000ull
- #define VC_VXF_HIDE_VINFO 0x04000000ull
- #define VC_VXF_STATE_SETUP (1ULL<<32)
- #define VC_VXF_STATE_INIT (1ULL<<33)
- #define VC_VXF_STATE_ADMIN (1ULL<<34)
- #define VC_VXF_SC_HELPER (1ULL<<36)
- #define VC_VXF_REBOOT_KILL (1ULL<<37)
- #define VC_VXF_PERSISTENT (1ULL<<38)
- #define VC_VXF_FORK_RSS (1ULL<<48)
- #define VC_VXF_PROLIFIC (1ULL<<49)
- #define VC_VXF_IGNEG_NICE (1ULL<<52)
- #define VC_VXF_IGNEG_IONICE (1ULL<<53)
- #define VC_VXC_SET_UTSNAME 0x00000001ull
- #define VC_VXC_SET_RLIMIT 0x00000002ull
- #define VC_VXC_FS_SECURITY 0x00000004ull
- #define VC_VXC_TIOCSTI 0x00000010ull
- #define VC_VXC_RAW_ICMP 0x00000100ull
- #define VC_VXC_SYSLOG 0x00001000ull
- #define VC_VXC_OOM_ADJUST 0x00002000ull
- #define VC_VXC_AUDIT_CONTROL 0x00004000ull
- #define VC_VXC_SECURE_MOUNT 0x00010000ull
- #define VC_VXC_SECURE_REMOUNT 0x00020000ull
- #define VC_VXC_BINARY_MOUNT 0x00040000ull
- #define VC_VXC_QUOTA_CTL 0x00100000ull
- #define VC_VXC_ADMIN_MAPPER 0x00200000ull
- #define VC_VXC_ADMIN_CLOOP 0x00400000ull
- #define VC_VXC_KTHREAD 0x01000000ull
- #define VC_VXC_NAMESPACE 0x02000000ull
- #define VC_VXSM_FILL_RATE 0x0001
- #define VC_VXSM_INTERVAL 0x0002

- `#define VC_VXSM_FILL_RATE2 0x0004`
- `#define VC_VXSM_INTERVAL2 0x0008`
- `#define VC_VXSM_TOKENS 0x0010`
- `#define VC_VXSM_TOKENS_MIN 0x0020`
- `#define VC_VXSM_TOKENS_MAX 0x0040`
- `#define VC_VXSM_PRIO_BIAS 0x0100`
- `#define VC_VXSM_CPU_ID 0x1000`
- `#define VC_VXSM_BUCKET_ID 0x2000`
- `#define VC_VXSM_IDLE_TIME 0x0200`
- `#define VC_VXSM_FORCE 0x0400`
- `#define VC_VXSM_MSEC 0x4000`
- `#define VC_VXSM_V3_MASK 0x0173`
- `#define VC_NXF_INFO_LOCK 0x00000001ull`
- `#define VC_NXF_INFO_PRIVATE 0x00000008ull`
- `#define VC_NXF_SINGLE_IP 0x00000100ull`
- `#define VC_NXF_LBACK_REMAP 0x00000200ull`
- `#define VC_NXF_LBACK_ALLOW 0x00000400ull`
- `#define VC_NXF_HIDE_NETIF 0x02000000ull`
- `#define VC_NXF_HIDE_LBACK 0x04000000ull`
- `#define VC_NXF_STATE_SETUP (1ULL<<32)`
- `#define VC_NXF_STATE_ADMIN (1ULL<<34)`
- `#define VC_NXF_SC_HELPER (1ULL<<36)`
- `#define VC_NXF_PERSISTENT (1ULL<<38)`
- `#define VC_NXC_TUN_CREATE 0x00000001ull`
- `#define VC_NXC_RAW_ICMP 0x00000100ull`
- `#define VC_VLIMIT_NSOCK 16`
- `#define VC_VLIMIT_OPENFD 17`
- `#define VC_VLIMIT_ANON 18`
- `#define VC_VLIMIT_SHMEM 19`
- `#define VC_VLIMIT_SEMARY 20`
- `#define VC_VLIMIT_NSEMS 21`
- `#define VC_VLIMIT_DENTRY 22`
- `#define VC_VLIMIT_MAPPED 23`
- `#define VC_VCI_NO_DYNAMIC (1 << 0)`
- `#define VC_VCI_SPACES (1 << 10)`
- `#define VC_VCI_NETV2 (1 << 11)`
- `#define VC_VCI_PPTAG (1 << 28)`
- `#define VC_DATTR_CREATE 0x00000001`
- `#define VC_DATTR_OPEN 0x00000002`
- `#define VC_DATTR_REMAP 0x00000010`
- `#define VC_VXM_SET_INIT 0x00000001`
- `#define VC_VXM_SET_REAPER 0x00000002`
- `#define VC_NXA_TYPE_IPV4 0x0001`
- `#define VC_NXA_TYPE_IPV6 0x0002`
- `#define VC_NXA_TYPE_NONE 0x0000`
- `#define VC_NXA_TYPE_ANY 0x00FF`
- `#define VC_NXA_TYPE_ADDR 0x0010`
- `#define VC_NXA_TYPE_MASK 0x0020`
- `#define VC_NXA_TYPE_RANGE 0x0040`
- `#define VC_NXA_MOD_BCAST 0x0100`

- #define [VC_NXA_MOD_LBACK](#) 0x0200
- #define [CLONE_NEWNS](#) 0x00020000
- #define [CLONE_NEWUTS](#) 0x04000000
- #define [CLONE_NEWIPC](#) 0x08000000
- #define [CLONE_NEWUSER](#) 0x10000000
- #define [CLONE_NEWPID](#) 0x20000000
- #define [CLONE_NEWNET](#) 0x40000000
- #define [VC_BAD_PERSONALITY](#) ((uint_least32_t)(-1))
- #define [vna_v4_ip](#) s.ip.v4
- #define [vna_v4_ip2](#) s.ip2.v4
- #define [vna_v4_mask](#) s.mask.v4
- #define [vna_v6_ip](#) s.ip.v6
- #define [vna_v6_ip2](#) s.ip2.v6
- #define [vna_v6_mask](#) s.mask.v6
- #define [VC_LIMIT_VSERVER_NAME_LEN](#) 1024
- #define [vcSKEL_INTERFACES](#) 1u
- #define [vcSKEL_PKGMGMT](#) 2u
- #define [vcSKEL_FILESYSTEM](#) 4u

Typedefs

- typedef an_unsigned_integer_type [xid_t](#)
- typedef an_unsigned_integer_type [nid_t](#)
- typedef an_unsigned_integer_type [tag_t](#)
- typedef uint64_t [vc_vci_t](#)
- typedef uint_least64_t [vc_limit_t](#)

The type which is used for a single limit value.

Enumerations

- enum [vc_uts_type](#) {
[vcVHI_CONTEXT](#), [vcVHI_SYSNAME](#), [vcVHI_NODENAME](#), [vcVHI_RELEASE](#),
[vcVHI_VERSION](#), [vcVHI_MACHINE](#), [vcVHI_DOMAINNAME](#) }
- enum [vcFeatureSet](#) {
[vcFEATURE_VKILL](#), [vcFEATURE_IATTR](#), [vcFEATURE_RLIMIT](#), [vcFEATURE_-COMPAT](#),
[vcFEATURE_MIGRATE](#), [vcFEATURE_NAMESPACE](#), [vcFEATURE_SCHED](#), [vcFEATURE_VINFO](#),
[vcFEATURE_VHI](#), [vcFEATURE_VSHELPER0](#), [vcFEATURE_VSHELPER](#), [vcFEATURE_-VWAIT](#),
[vcFEATURE_VNET](#), [vcFEATURE_VSTAT](#), [vcFEATURE_PPTAG](#), [vcFEATURE_-PIDSPACE](#),
[vcFEATURE_SPACES](#), [vcFEATURE_PERSISTENT](#), [vcFEATURE_PIVOT_ROOT](#) }
- enum [vcXidType](#) {
[vcTYPE_INVALID](#), [vcTYPE_MAIN](#), [vcTYPE_WATCH](#), [vcTYPE_STATIC](#),
[vcTYPE_DYNAMIC](#) }

- enum `vcCfgStyle` {
 `vcCFG_NONE`, `vcCFG_AUTO`, `vcCFG_LEGACY`, `vcCFG_RECENT_SHORT`,
 `vcCFG_RECENT_FULL` }
- enum `vcCtxType` { `vcCTX_XID` = 1, `vcCTX_NID`, `vcCTX_TAG` }

Functions

- int `vc_syscall` (uint32_t cmd, `xid_t` xid, void *data)
 The generic vserver syscall
 This function executes the generic vserver syscall. It uses the correct syscallnumber (which may differ between the different architectures).
- int `vc_get_version` ()
 Returns the version of the current kernel API.
- `vc_vci_t` `vc_get_vci` ()
 Returns the kernel configuration bits.
- `xid_t` `vc_new_s_context` (`xid_t` ctx, unsigned int remove_cap, unsigned int flags)
 Moves current process into a context
 Puts current process into context ctx, removes the capabilities given in remove_cap and sets flags.
- int `vc_set_ipv4root` (uint32_t bcast, size_t nb, struct `vc_ip_mask_pair` const *ips)
 Sets the ipv4root information.
- size_t `vc_get_nb_ipv4root` () VC_ATTR_CONST
 Returns the value of NB_IPV4ROOT.
 *This function returns the value of NB_IPV4ROOT which was used when the library was built, but **not** the value which is used by the currently running kernel.*
- `xid_t` `vc_ctx_create` (`xid_t` xid, struct `vc_ctx_flags` *flags)
 Creates a context without starting it.
 This functions initializes a new context. When already in a freshly created context, this old context will be discarded.
- int `vc_ctx_migrate` (`xid_t` xid, uint_least64_t flags)
 Moves the current process into the specified context.
- int `vc_ctx_stat` (`xid_t` xid, struct `vc_ctx_stat` *stat)
 Get some statistics about a context.
- int `vc_virt_stat` (`xid_t` xid, struct `vc_virt_stat` *stat)
 Get more statistics about a context.
- int `vc_ctx_kill` (`xid_t` ctx, pid_t pid, int sig)
 Sends a signal to a context/pid
 Special values for pid are:
 - -1 which means every process in ctx except the init-process
 - 0 which means every process in ctx inclusive the init-process.

- `int vc_get_cflags (xid_t xid, struct vc_ctx_flags *)`
- `int vc_set_cflags (xid_t xid, struct vc_ctx_flags const *)`
- `int vc_get_ccaps (xid_t xid, struct vc_ctx_caps *)`
- `int vc_set_ccaps (xid_t xid, struct vc_ctx_caps const *)`
- `int vc_get_vx_info (xid_t xid, struct vc_vx_info *info)`
- `xid_t vc_get_task_xid (pid_t pid)`
Returns the context of the given process.
- `int vc_wait_exit (xid_t xid)`
Waits for the end of a context.
- `int vc_get_rlimit_mask (xid_t xid, struct vc_rlimit_mask *lim)`
Returns the limits supported by the kernel.
- `int vc_get_rlimit (xid_t xid, int resource, struct vc_rlimit *lim)`
Returns the limits of resource.
- `int vc_set_rlimit (xid_t xid, int resource, struct vc_rlimit const *lim)`
Sets the limits of resource.
- `int vc_rlimit_stat (xid_t xid, int resource, struct vc_rlimit_stat *stat)`
Returns the current stats of resource.
- `int vc_reset_minmax (xid_t xid)`
Resets the minimum and maximum observed values of all resources.
- `bool vc_parseLimit (char const *str, vc_limit_t *res)`
Parses a string describing a limit
This function parses str and interprets special words like "inf" or suffixes. Valid suffixes are
 - k ... 1000
 - m ... 1000000
 - K ... 1024
 - M ... 1048576.
- `nid_t vc_get_task_nid (pid_t pid)`
- `int vc_get_nx_info (nid_t nid, struct vc_nx_info *)`
- `nid_t vc_net_create (nid_t nid)`
- `int vc_net_migrate (nid_t nid)`
- `int vc_net_add (nid_t nid, struct vc_net_addr const *info)`
- `int vc_net_remove (nid_t nid, struct vc_net_addr const *info)`
- `int vc_get_nflags (nid_t, struct vc_net_flags *)`
- `int vc_set_nflags (nid_t, struct vc_net_flags const *)`
- `int vc_get_ncaps (nid_t, struct vc_net_caps *)`
- `int vc_set_ncaps (nid_t, struct vc_net_caps const *)`
- `int vc_set_iattr (char const *filename, xid_t xid, uint_least32_t flags, uint_least32_t mask)`
- `int vc_fset_iattr (int fd, xid_t xid, uint_least32_t flags, uint_least32_t mask)`
- `int vc_get_iattr (char const *filename, xid_t *xid, uint_least32_t *flags, uint_least32_t *mask)`
Returns information about attributes and assigned context of a file.
This function returns the VC_IATTR_XXX flags and about the assigned context of a file. To request an information, the appropriate bit in mask must be set and the corresponding parameter (xid or flags) must not be NULL.

- `int vc_fget_iattr` (`int fd`, `xid_t *xid`, `uint_least32_t *flags`, `uint_least32_t *mask`)
- `xid_t vc_getfilecontext` (`char const *filename`)

Returns the context of filename
This function calls `vc_get_iattr()` with appropriate arguments to determine the context of filename. In error-case or when no context is assigned, `VC_NOCTX` will be returned. To differ between both cases, `errno` must be examined.
- `int vc_set_vhi_name` (`xid_t xid`, `vc_uts_type` type, `char const *val`, `size_t len`)
- `int vc_get_vhi_name` (`xid_t xid`, `vc_uts_type` type, `char *val`, `size_t len`)
- `int vc_enter_namespace` (`xid_t xid`, `uint_least64_t mask`, `uint32_t index`)
- `int vc_set_namespace` (`xid_t xid`, `uint_least64_t mask`, `uint32_t index`)
- `int vc_cleanup_namespace` (`void`)
- `uint_least64_t vc_get_space_mask` (`void`)
- `uint_least64_t vc_get_space_default` (`void`)
- `int vc_add_dlimit` (`char const *filename`, `xid_t xid`, `uint_least32_t flags`)
- `int vc_rem_dlimit` (`char const *filename`, `xid_t xid`, `uint_least32_t flags`)
- `int vc_set_dlimit` (`char const *filename`, `xid_t xid`, `uint_least32_t flags`, `struct vc_ctx_dlimit const *limits`)
- `int vc_get_dlimit` (`char const *filename`, `xid_t xid`, `uint_least32_t flags`, `struct vc_ctx_dlimit *limits`)
- `tag_t vc_get_task_tag` (`pid_t pid`)
- `int vc_tag_create` (`tag_t tag`)
- `int vc_tag_migrate` (`tag_t tag`)
- `int vc_set_sched` (`xid_t xid`, `struct vc_set_sched const *`)
- `int vc_get_sched` (`xid_t xid`, `struct vc_set_sched *`)
- `int vc_sched_info` (`xid_t xid`, `struct vc_sched_info *info`)
- `int vc_set_mapping` (`xid_t xid`, `const char *device`, `const char *target`, `uint32_t flags`)
- `int vc_unset_mapping` (`xid_t xid`, `const char *device`, `const char *target`, `uint32_t flags`)
- `int vc_get_badness` (`xid_t xid`, `int64_t *badness`)
- `int vc_set_badness` (`xid_t xid`, `int64_t badness`)
- `uint_least64_t vc_text2bcap` (`char const *str`, `size_t len`)

Converts a single string into bcapability.
- `char const * vc_lobcap2text` (`uint_least64_t *val`)

Converts the lowest bit of a bcapability or the entire value (when possible) to a textual representation.
- `int vc_list2bcap` (`char const *str`, `size_t len`, `struct vc_err_listparser *err`, `struct vc_ctx_caps *cap`)

Converts a string into a bcapability-bitmask
Syntax of str:.
- `uint_least64_t vc_text2ccap` (`char const *`, `size_t len`)
- `char const * vc_loccap2text` (`uint_least64_t *`)
- `int vc_list2ccap` (`char const *`, `size_t len`, `struct vc_err_listparser *err`, `struct vc_ctx_caps *`)
- `int vc_list2cflag` (`char const *`, `size_t len`, `struct vc_err_listparser *err`, `struct vc_ctx_flags *flags`)
- `uint_least64_t vc_text2cflag` (`char const *`, `size_t len`)
- `char const * vc_locflag2text` (`uint_least64_t *`)
- `uint_least32_t vc_list2cflag_compat` (`char const *`, `size_t len`, `struct vc_err_listparser *err`)
- `uint_least32_t vc_text2cflag_compat` (`char const *`, `size_t len`)
- `char const * vc_hicflag2text_compat` (`uint_least32_t`)
- `int vc_text2cap` (`char const *`)
- `char const * vc_cap2text` (`unsigned int`)

- int **vc_list2nflag** (char const *, size_t len, struct [vc_err_listparser](#) *err, struct [vc_net_flags](#) *flags)
- uint_least64_t **vc_text2nflag** (char const *, size_t len)
- char const * **vc_lonflag2text** (uint_least64_t *)
- uint_least64_t **vc_text2ncap** (char const *, size_t len)
- char const * **vc_loncap2text** (uint_least64_t *)
- int **vc_list2ncap** (char const *, size_t len, struct [vc_err_listparser](#) *err, struct [vc_net_caps](#) *)
- uint_least64_t **vc_get_insecurebcaps** () VC_ATTR_CONST
- uint_least32_t **vc_text2personalityflag** (char const *str, size_t len)
- char const * **vc_lpersonality2text** (uint_least32_t *)
- int **vc_list2personalityflag** (char const *, size_t len, uint_least32_t *personality, struct [vc_err_listparser](#) *err)
- uint_least32_t **vc_str2personalitytype** (char const *, size_t len)
- bool **vc_isSupported** ([vcFeatureSet](#)) VC_ATTR_CONST
- bool **vc_isSupportedString** (char const *)
- [vcXidType](#) **vc_getXIDType** ([xid_t](#) xid) VC_ATTR_CONST
- bool **vc_is_dynamic_xid** ([xid_t](#) xid)
- [xid_t](#) **vc_xidopt2xid** (char const *, bool honor_static, char const **err_info)
- [nid_t](#) **vc_nidopt2nid** (char const *, bool honor_static, char const **err_info)
- [tag_t](#) **vc_tagopt2tag** (char const *, bool honor_static, char const **err_info)
- [vcCfgStyle](#) **vc_getVserverCfgStyle** (char const *id)
- char * **vc_getVserverName** (char const *id, [vcCfgStyle](#) style)
- char * **vc_getVserverCfgDir** (char const *id, [vcCfgStyle](#) style)
- char * **vc_getVserverAppDir** (char const *id, [vcCfgStyle](#) style, char const *app)
- char * **vc_getVserverVdir** (char const *id, [vcCfgStyle](#) style, bool physical)
- [xid_t](#) **vc_getVserverCtx** (char const *id, [vcCfgStyle](#) style, bool honor_static, bool *is_running, [vc-CtxType](#) type)
- char * **vc_getVserverByCtx** ([xid_t](#) ctx, [vcCfgStyle](#) *style, char const *revdir)
- int **vc_compareVserverById** (char const *lhs, [vcCfgStyle](#) lhs_style, char const *rhs, [vcCfgStyle](#) rhs_style)
- void **vc_exitLikeProcess** (int pid, int ret)
- int **vc_createSkeleton** (char const *id, [vcCfgStyle](#) style, int flags)

6.2.1 Detailed Description

The public interface of the the libvserver library.

Definition in file [vserver.h](#).

6.2.2 Define Documentation

6.2.2.1 #define VC_DYNAMIC_XID (([xid_t](#))(-1))

the value which means a random (the next free) ctx

Definition at line 67 of file [vserver.h](#).

6.2.2.2 #define VC_NOCTX (([xid_t](#))(-1))

the value which is returned in error-case (no ctx found)

Definition at line 64 of file [vserver.h](#).

6.2.2.3 #define VC_SAMECTX (([xid_t](#))(-2))

the value which means the current ctx

Definition at line 69 of file vserver.h.

6.2.3 Typedef Documentation

6.2.3.1 typedef uint_least64_t [vc_limit_t](#)

The type which is used for a single limit value.

Special values are

- VC_LIM_INFINITY ... which is the infinite value
- VC_LIM_KEEP ... which is used to mark values which shall not be modified by the [vc_set_rlimit\(\)](#) operation.

Else, the interpretation of the value depends on the corresponding resource; it might be bytes, pages, seconds or litres of beer.

Definition at line 554 of file vserver.h.

6.2.3.2 an_unsigned_integer_type [xid_t](#)

The identifier of a context.

Definition at line 349 of file vserver.h.

6.2.4 Function Documentation

6.2.4.1 int [vc_add_dlimit](#) (char const **filename*, [xid_t](#) *xid*, uint_least32_t *flags*)

Add a disk limit to a file system.

6.2.4.2 int [vc_createSkeleton](#) (char const **id*, [vcCfgStyle](#) *style*, int *flags*)

Create a basic configuration skeleton for a vserver plus toplevel directories for pkgmanagemt and filesystem (when requested).

6.2.4.3 int [vc_get_dlimit](#) (char const **filename*, [xid_t](#) *xid*, uint_least32_t *flags*, struct [vc_ctx_dlimit](#) **limits*)

Get a disk limit.

6.2.4.4 [tag_t](#) [vc_get_task_tag](#) (pid_t *pid*)

Get the filesystem tag for a process.

6.2.4.5 char* [vc_getVserverAppDir](#) (char const **id*, [vcCfgStyle](#) *style*, char const **app*)

Returns the path of the configuration directory for the given application. The result will be allocated and must be freed by the caller.

6.2.4.6 `char* vc_getVserverByCtx (xid_t ctx, vcCfgStyle * style, char const * revdir)`

Resolves the cfg-path of the vserver owning the given ctx. 'revdir' will be used as the directory holding the mapping-links; when NULL, the default value will be assumed. The result will be allocated and must be freed by the caller.

6.2.4.7 `char* vc_getVserverCfgDir (char const * id, vcCfgStyle style)`

Returns the path of the vserver configuration directory. When the given vserver does not exist, or when it does not have such a directory, NULL will be returned. Else, the result will be allocated and must be freed by the caller.

6.2.4.8 `xid_t vc_getVserverCtx (char const * id, vcCfgStyle style, bool honor_static, bool * is_running, vcCtxType type)`

Returns the ctx of the given vserver. When vserver is not running and 'honor_static' is false, VC_NOCTX will be returned. Else, when 'honor_static' is true and a static assignment exists, those value will be returned. Else, the result will be VC_NOCTX.

When 'is_running' is not null, the status of the vserver will be assigned to this variable.

6.2.4.9 `char* vc_getVserverName (char const * id, vcCfgStyle style)`

Resolves the name of the vserver. The result will be allocated and must be freed by the caller.

6.2.4.10 `char* vc_getVserverVdir (char const * id, vcCfgStyle style, bool physical)`

Returns the path to the vserver root-directory. The result will be allocated and must be freed by the caller.

6.2.4.11 `bool vc_is_dynamic_xid (xid_t xid)`

Returns true iff *xid* is a dynamic xid

6.2.4.12 `nid_t vc_nidopt2nid (char const *, bool honor_static, char const ** err_info)`

Maps a nid given at '-nid' options to a nid_t

6.2.4.13 `int vc_rem_dlimit (char const * filename, xid_t xid, uint_least32_t flags)`

Remove a disk limit from a file system.

6.2.4.14 `int vc_set_dlimit (char const * filename, xid_t xid, uint_least32_t flags, struct vc_ctx_dlimit const * limits)`

Set a disk limit.

6.2.4.15 `int vc_tag_create (tag_t tag)`

Create a new filesystem tag space.

6.2.4.16 `int vc_tag_migrate (tag_t tag)`

Migrate to an existing filesystem tag space.

6.2.4.17 `tag_t` `vc_tagopt2tag (char const *, bool honor_static, char const ** err_info)`

Maps a tag given at '-tag' options to a tag_t

6.2.4.18 `xid_t` `vc_xidopt2xid (char const *, bool honor_static, char const ** err_info)`

Maps an xid given at '-xid' options to an xid_t

Index

helper

- [vc_list2bcap](#), 8
- [vc_lobcap2text](#), 9
- [vc_parseLimit](#), 9
- [vc_text2bcap](#), 10

Helper functions, 8

[internal.h](#), 18

[Mapping_uint32](#), 10

[Mapping_uint64](#), 10

Syscall wrappers, 2

syscalls

- [vc_ctx_create](#), 3
- [vc_ctx_migrate](#), 4
- [vc_ctx_stat](#), 4
- [vc_get_iattr](#), 4
- [vc_get_rlimit](#), 5
- [vc_get_task_xid](#), 5
- [vc_get_vci](#), 5
- [vc_get_version](#), 5
- [vc_getfilecontext](#), 5
- [vc_new_s_context](#), 6
- [vc_reset_minmax](#), 6
- [vc_rlimit_stat](#), 6
- [vc_set_ipv4root](#), 7
- [vc_set_rlimit](#), 7
- [vc_syscall](#), 7
- [vc_virt_stat](#), 7

[vc_add_dlimit](#)
[vserver.h](#), 30

[vc_createSkeleton](#)
[vserver.h](#), 30

[vc_ctx_caps](#), 11

[vc_ctx_create](#)
[syscalls](#), 3

[vc_ctx_dlimit](#), 11

[vc_ctx_flags](#), 12

[vc_ctx_migrate](#)
[syscalls](#), 4

[vc_ctx_stat](#), 12
[syscalls](#), 4

[VC_DYNAMIC_XID](#)
[vserver.h](#), 29

[vc_err_listparser](#), 13

[vc_get_dlimit](#)
[vserver.h](#), 30

[vc_get_iattr](#)
[syscalls](#), 4

[vc_get_rlimit](#)
[syscalls](#), 5

[vc_get_task_tag](#)
[vserver.h](#), 30

[vc_get_task_xid](#)
[syscalls](#), 5

[vc_get_vci](#)
[syscalls](#), 5

[vc_get_version](#)
[syscalls](#), 5

[vc_getfilecontext](#)
[syscalls](#), 5

[vc_getVserverAppDir](#)
[vserver.h](#), 30

[vc_getVserverByCtx](#)
[vserver.h](#), 30

[vc_getVserverCfgDir](#)
[vserver.h](#), 30

[vc_getVserverCtx](#)
[vserver.h](#), 31

[vc_getVserverName](#)
[vserver.h](#), 31

[vc_getVserverVdir](#)
[vserver.h](#), 31

[vc_ip_mask_pair](#), 13

[vc_is_dynamic_xid](#)
[vserver.h](#), 31

[vc_limit_t](#)
[vserver.h](#), 30

[vc_list2bcap](#)
[helper](#), 8

[vc_lobcap2text](#)
[helper](#), 9

[vc_net_addr](#), 14

[vc_net_caps](#), 14

[vc_net_flags](#), 14

[vc_new_s_context](#)
[syscalls](#), 6

[vc_nidopt2nid](#)
[vserver.h](#), 31

[VC_NOCTX](#)
[vserver.h](#), 29

[vc_nx_info](#), 15

[vc_parseLimit](#)
[helper](#), 9

[vc_rem_dlimit](#)
[vserver.h](#), 31

[vc_reset_minmax](#)
[syscalls](#), 6

[vc_rlimit](#), 15

vc_rlimit_mask, 16
vc_rlimit_stat, 16
 syscalls, 6
VC_SAMECTX
 vserver.h, 29
vc_sched_info, 17
vc_set_dlimit
 vserver.h, 31
vc_set_ipv4root
 syscalls, 7
vc_set_rlimit
 syscalls, 7
vc_set_sched, 17
vc_syscall
 syscalls, 7
vc_tag_create
 vserver.h, 31
vc_tag_migrate
 vserver.h, 31
vc_tagopt2tag
 vserver.h, 31
vc_text2bcap
 helper, 10
vc_virt_stat, 18
 syscalls, 7
vc_vx_info, 18
vc_xidopt2xid
 vserver.h, 31
vserver.h, 20
 vc_add_dlimit, 30
 vc_createSkeleton, 30
 VC_DYNAMIC_XID, 29
 vc_get_dlimit, 30
 vc_get_task_tag, 30
 vc_getVserverAppDir, 30
 vc_getVserverByCtx, 30
 vc_getVserverCfgDir, 30
 vc_getVserverCtx, 31
 vc_getVserverName, 31
 vc_getVserverVdir, 31
 vc_is_dynamic_xid, 31
 vc_limit_t, 30
 vc_nidopt2nid, 31
 VC_NOCTX, 29
 vc_rem_dlimit, 31
 VC_SAMECTX, 29
 vc_set_dlimit, 31
 vc_tag_create, 31
 vc_tag_migrate, 31
 vc_tagopt2tag, 31
 vc_xidopt2xid, 31
 xid_t, 30

xid_t